1 Node Descriptor 52 – Airflow sensor

1.1 Device Description

The Airflow sensor uses a flexible, stress sensitive ribbon to detect air flow within

1.2 Hardware Details

1.2.1 Flex Ribbon

Possible hardware combinations include:

- Platform RFSC Rev A, Ver 0: Not Supported.
- Platform RFSC Rev B, Ver 0: Supported.
- Platform RFSC Rev C, Ver 0: Supported.
- Platform MoWi Rev 2, Ver x: Not Supported.

Length	4 mm
Resistance range	$3.0k\Omega - 9.0k\Omega$
Life Cycle	1,000,000
Hysteresis	7%
Resolution	1° bend
Temperature Range	-35°C - +85°C
Humidity Range	0-95% RH

1.3 Enclosure Details

This sensor is available in WIT and WIT2. Not available in Industrial or MoWi.

1.4 Message Details

1.4.1 STATE (SOM, SDM)

Both the Spurious Orphan Message (SOM) and the Spurious Data Message (SDM) contain the STATE field. STATE is defined here

Field	Length	Description
Test Active	1 bit LSB	Test state is active (1) or inactive (0)
Aware State	1 bit	Aware State is active (1) or inactive (0)
Sensor Disable	1 bit	Sensor is disable (communication still happens)
RSVD	1 bit	Currently not used
Calibrate Active	1 bit	Not used.
Self Test Status	1 bit	Always set to 0, not used.
Not used	1 bit	
Not used	1 bit MSB	

This application specifies no action control types.

1.4.2 SDATA (SDM)

The Spurious Data Message contains the SDATA field, which is defined here. The SDATA field is defaulted to bytes for this application.

SDATA[0]: STATE

SDATA[1]: Detected presence or absence of moving air.

SDATA[2-5]: Value of resistance in ohms.

Field	Length	Value	Format
SDATA[0]	1 byte	Int8	STATE
SDATA[1]	1 byte	Int8	Current state, either Still Air (0), or Moving Air (1).
SDATA[2-5]	4 bytes	Int32	Value of resistance in ohms.

1.5 General Configuration Defaults

The Configuration Defaults below are native to the Air Flow sensor only.

Field	Default	Min	Max	Comments
NODEDESC	52	N/A	N/A	Fixed.

1.6 Profile Defaults

The Flex sensor operates using the Interval device profile.

Field	Default	Min	Max	Comments
PROFILE	1	N/A	N/A	1=Interval profile.
MRES	1	1	250	Measurements per heartbeat
SYNCMASK	0	0	0x00FF	Synchronization or offset of heartbeats.
HYST	0	0	9000	Buffer zone around a threshold value.
THRSHMIN	3000	0	9000	Trip resistance low.
THRSHMAX	9000	0	90000	Trip resistance high.
CALVAL_1	1000	1	65535	Test Interval in milliseconds.
CALVAL_2	2	1	65535	When trip resistance is breached, the number of additional measurements that must be exceed the trip resistance in order to qualify a state change from moving air to still air and vice versa.
CALVAL_3	1	0	1	Trigger type: 0 for aware on still, 1 for aware on air moving
CALVAL_4	1000	0	65535	Exact fixed bias resistor value.